

WireGuard VPN



INSTALL WIREGUARD

```
$ apt install wireguard
```

```
# Move the wireguard directory
```

```
$ cd /etc/wireguard
```

CREATE KEYS FOR SERVER AND CLIENT

```
$ umask 077
```

```
$ wg genkey | tee private_key_server | wg pubkey >  
public_key_server
```

```
$ umask 077
```

```
$ wg genkey | tee private_key_client | wg pubkey >  
public_key_client
```

```
# Print keys to terminal for copying
```

```
cat private_key_server
```

```
cat public_key_server
cat private_key_client
cat public_key_client
```

CREATE .CONF FILE FOR SERVER

```
$ umask 077
$ nano wg0.conf
```

[Interface]

Address = 192.168.20.1/24

SaveConfig = true

ListenPort = 41194

PrivateKey = # private_key_server

**PostUp = iptables -A FORWARD -i %i -j ACCEPT; iptables -t
nat -A POSTROUTING -o eth0 -j MASQUERADE**

```
PostDown = iptables -D FORWARD -i %i -j ACCEPT; iptables  
-t nat -D POSTROUTING -o eth0 -j MASQUERADE
```

```
[Peer]
```

```
PublicKey = # public_key_client
```

```
AllowedIPs = 192.168.20.2/32
```

CREATE .CONF FILE FOR CLIENT

```
$ umask 077
```

```
$ nano wg0-client.conf
```

```
[Interface]
```

```
Address = 192.168.20.2/32
```

```
PrivateKey = # private_key_client
```

```
DNS = 192.168.20.1
```

```
[Peer]
```

```
PublicKey = # public_key_server
```

```
Endpoint = # Server IP:41194
```

AllowedIPs = 0.0.0.0/0

PersistentKeepalive = 25

FIREWALL RULES

\$ ufw enable

ufw allow 41194/udp

ufw allow 22/tcp

ufw allow from 192.168.20.0/24

\$ ufw status

NETWORK RULES

Uncomment line in for packet forwarding

\$ nano /etc/sysctl.conf

net.ipv4.ip_forward=1

\$ sysctl -p

INSTALL RESOLVCONF

```
$ apt install resolvconf
```

```
$ nano /etc/resolvconf/resolv.conf.d/head
```

```
# Add the following lines
```

```
nameserver 1.1.1.1
```

```
nameserver 1.0.0.1
```

```
$ systemctl start resolvconf.service
```

```
$ systemctl status resolvconf.service
```

WIREGUARD COMMANDS

```
# Enable to start at boot-up
```

```
$ systemctl enable wg-quick@wg0
```

Start to.. well, start

\$ systemctl start wg-quick@wg0

Status of wg

\$ systemctl status wg-quick@wg0

Stops service to edit conf files

\$ systemctl stop wg-quick@wg0

\$ wg-quick up wg0

\$ wg-quick down wg0

\$ wg

\$ wg show

\$ ip a show wg0

\$ resolvectl status

\$ systemd-resolve --status

IOS QRCODE -for iphone client app

\$ apt install qrencode

```
$ qrencode -t ansiutf8 < /etc/wireguard/wg0-client.conf
```

learn iptables / ufw firewall rules

learn permissions for files chmod / umask

learn vim / nano editors

learn PuTTY shortcuts

learn port knocking / fail2

